

## Chapter 1 : printer - How can I print out a PDF substituting pixels for blue pixels? - Super User

*Then scroll down to the Printer Features Common section and change the Ink Set option to Color. Hit Apply. The printer will now print using only the ink from the color cartridge.*

The printers listed in this document cannot print when one ink cartridge is empty. Your printer is designed to print only when all ink cartridges have ink. Some ink from all the ink cartridges is used in periodic servicing tasks. This helps to prevent issues such as printhead clogs and poor print quality. There is no way to bypass this feature. The printer generates these different messages as cartridges are used: Thank you for installing Genuine HP cartridges! Redeem your HP Reward! Cartridge Low – you can continue printing, but HP recommends that you have a replacement cartridge on hand. Use Black Ink Only? You can print either in grayscale or in composite black. You must replace the cartridge soon. This message might not appear in some cases, depending on how you print. Cartridges Depleted – one of the cartridges is out of ink and the printer has only enough ink in the system for servicing tasks. You must replace the cartridge to resume printing. Replace the empty ink cartridge When an ink cartridge is depleted, you must replace it before you can print. Purchase replacement cartridges and other supplies from the HP Store or local retailers. Change print settings to print in grayscale optional If one or more color ink cartridges are low but not empty and you want to minimize the use of color ink, change the settings in the HP software to print with black ink only grayscale. If you print with black ink only, the other ink cartridges must have ink for the printer to print. If you print with black ink only, the printer still uses small amounts of ink from all the ink cartridges for occasional servicing tasks. HP recommends that you replace any low ink cartridges to avoid any interruptions in printing. You must have the full feature printer software installed on your computer to change this print setting. I do not have the full feature software If you do not have the full feature software, follow these steps to download and install the most recent version of your printer software. Turn on the printer. Disconnect the USB cable from the printer, if necessary. The software installation prompts you to connect the cable if needed. If you need to change the operating system, click Change, select your version, and then click Change. Under the Driver heading, click Download for the full software package, or click Basic Drivers for other driver options. Set grayscale print properties Windows Change the print settings to print with black ink only. You might need to change your print settings every time you print. These steps vary by software, program, and operating system. In your software application, click Print. Select your printer from the list of available printers. Click the option that opens the Printer Properties dialog box. Depending on your software application, this option might be called Printer Properties, Options, Printer Setup, Printer, or Preferences. To use even less black ink, select the Draft setting. Click OK, and then click Print to start the print job. When you print in color, you must turn off the grayscale setting in the Printer Properties, Options, Printer Setup, Printer, or Preferences window. Set grayscale print properties Mac OS X Follow these steps to set the print settings to print with black ink only. Click the triangle next to Color Options. Select Black Print ink cartridge Only, and then click Print to start the print job. Frequently asked questions FAQs Review the following frequently asked questions for additional help. The printer must reserve enough ink for the servicing tasks that keep the printhead functioning. If there is enough ink for servicing and for printing with black ink only, or color ink only, then that message displays. If there is not enough ink for both printing and servicing, then the cartridge must be replaced. To prevent clogs in the printing mechanism and other print quality issues, some ink must be available in all the cartridges to perform periodic servicing tasks. How do I replace an ink cartridge? Steps to replace an ink cartridge vary by printer. For more information, go to HP Customer Support , type your printer model, and then search for replacing ink cartridges. My new ink cartridge is not working. What do I do? If you bought a new ink cartridge, and it is not working, or the printer indicates that it is empty, check the ink cartridge warranty status. If you have a defective cartridge or printhead, it might be under warranty. To check the warranty on your ink or toner supplies, go to hp. I typically print in black and white only, so why are my color ink cartridges empty? To decrease grain, some black areas might be printed with a mix of black and color inks. If you follow the steps in this document to print with black ink only, no color ink is used in printouts. This helps to prevent

issues like printhead clogs and poor print quality.

**Chapter 2 : HP Printers - Cannot Print When One HP Ink Cartridge is Empty | HP® Customer Support**

*To print a document that you cannot edit first, such as a web page [racedaydvl.com](http://racedaydvl.com) document from an e-mail, the process is longer. If your printer runs out of black ink, dark blue ink is commonly accepted. Printing from a Word Processor.*

The quality of a printed document or photo is not as expected. The procedures in this document should help with streaked or faded printouts, color or black ink not printing, documents with blurred or fuzzy text, ink streaks or smears, and other print quality problems. HP recommends that you use genuine HP ink or toner supplies. HP cannot guarantee the quality or reliability of non-HP or refilled cartridges. If you do not use genuine HP cartridges, the steps in this document might not resolve the issue. To check the authenticity of your cartridges, go to the HP anti-counterfeit webpage in English. Ink level warnings and indicators provide estimates for planning purposes only. When an indicator shows low ink levels, consider having a replacement cartridge available to avoid possible printing delays. You do not need to replace cartridges until you are prompted to. Check the paper note: This video shows how to fix print quality problems by checking the paper. Click here to see this video in full screen on YouTube. Use the following guidelines to make sure that the paper you are using is appropriate for the print job. If it is not, reload the product with an appropriate paper type. HP papers, inks, and printers are designed to work together. Many non-HP media could be incompatible with HP inks and printing systems. Use the correct paper type for your project: For everyday text documents, plain paper with ColorLok technology works well. For documents with dense printing, such as high contrast graphics or photographs, use HP Advanced Photo Paper for the best results. Load the paper print side down in the input tray. Many papers have printing and nonprinting sides. Do not use wrinkled or curled paper. Load only clean, wrinkle-free paper into the product. Store photo paper in its original packaging inside a resealable plastic bag. Store the paper on a flat surface in a cool, dry place. Load photo paper only when you are ready to print, and then put the unused paper back in the packaging. Try using a different paper. Paper that does not accept ink well is also prone to print defects. HP designs ink and paper to work together. Some media may not absorb ink as well as others. If your prints smear easily, make sure you are using a recommended paper. Plain paper with ColorLok technology is recommended for text printing. Figure: Horizontal streaks in printout. Continue with the following troubleshooting steps if your printout contains horizontal streaks, or other print-quality issues besides vertical streaks. Vertical streaks in printout. Do not replace cartridges or printheads for vertical streaks in a printout. Instead, check the paper as described earlier in this document, or search for a document that covers this issue. Vertical streaks in copies can often be fixed by cleaning the scanner glass. Check the print settings. Check the print settings to make sure that they are appropriate for your print job. In the software program you are trying to print from, click File and then click Print. The Print dialog box opens. Select your product, and then click Properties. The printer Properties dialog box opens. Click the Printing shortcuts tab. Under Printing shortcuts, click the type of job you are trying to print. Review the following options, and then make any necessary changes. Make sure that the selected option matches your paper size. If one of the options matches your paper type exactly, select that option. If you are not satisfied with your printed page quality, or want more densely printed prints, increase the print quality. To print more quickly, or for lighter prints, decrease the print quality. Click the Features tab. Check the Print in Grayscale setting. If you are trying to print in color, select Color Options, and then make sure that Print in Grayscale is not selected. If you are printing a black and white image, select Print in Grayscale to fix streaking in black areas. Click OK, and then click OK again to start the print job. Open a document and choose File, and then Print. Review the following options, and then make any necessary changes: If you are dissatisfied with the quality of your printouts, increase the print quality. To print more quickly, decrease the print quality. Click the Color Options pop-up or tab if it appears. If you want color printouts, make sure Grayscale is not selected if the option does not appear, it is not available for the printer. To save these settings for future print jobs, choose Save in the Presets menu, and then name the new preset. Print and evaluate a Print Quality Diagnostics Page. The Print Quality Diagnostics Page can help determine if the printer needs to be aligned or if the printheads need to be

cleaned or if the linefeed needs to be calibrated. Press the Setup button.

### Chapter 3 : how do I print in black without using my color ink - Canon Community

*Change the font color from black to blue by selecting blue from the font options in the main toolbar. You can also right-click and select "Font" from the list of options. Step. Print the document. You can select print from the main menu options, or you can press "Control" and "P" on your keyboard to print.*

The printer is not correctly connected to the computer Try one or more of these solutions: Turn off the printer and computer. Make sure the interface cable specifications match the specifications for the printer and computer. Make sure the interface cable is directly connected to the computer without passing through any device, such as a printer switching device, or extension cable. Your Epson printer is not selected as the default printer Install the printer driver if it is not installed yet, and follow the steps below to select your Epson printer as the default printer. Select Set As Default Printer, then close the window. Select Set As Default, then close the Printers window. Printer port setting does not match the printer connection port for Windows only To select the printer port, follow the steps below. Click the Ports tab. Make sure that your printer port is selected. Try one or more of these solutions: Run the Head Cleaning utility. For Windows, see Cleaning the print head. If the Head Cleaning utility does not work, replace the ink cartridges. See Replacing Ink Cartridges. Printouts are not what you expected Incorrect, garbled characters, or blank pages print Try one or more of these solutions: For Windows, clear any stalled print jobs from the Progress Meter. If the problem persists, turn off the printer and computer. Incorrect margins Try one or more of these solutions: Check the margin settings in your application. Make sure the margins are within the printable area of the page. For Windows, check the Borderless setting in the Paper menu. Make sure they are correct for the paper size you are using. See Making Settings on the Paper Menu. Make sure the paper set position is correct. See Making Advanced setting. Printed color differs from the color on the screen Try one or more of these solutions: Adjust the Color Density in the Paper Configuration dialog. For Windows, see Paper Configuration. Make sure the media type setting matches the paper being used. Since monitors and printers produce colors differently, printed colors will not always match on screen colors perfectly. However, the above color systems are provided to overcome color differences. See Printer Color Management. You can produce sharper images with more vivid colors. For Windows, select PhotoEnhance in the Advanced menu. For Windows, select Color Controls in the Advanced menu, and adjust color, brightness, etc. A ruled line shifts Perform the print head alignment. For Windows, see Aligning the print head. If the problem persists, perform the print head cleaning. Printout has smears on the bottom edge Try one or more of these solutions: If the paper is curled towards the printable side, flatten it or curl it slightly to the opposite side. See Making Settings on the Main Menu. Make sure it is correct for the paper you are using. See Making the paper settings. Print Quality Could be Better Click the caption under the illustration that best resembles your printout.

### Chapter 4 : Canon MP - only prints in blue!!! | MacRumors Forums

*Quick fix, don't try to change the printer doesn't happen you highlight the entire item your printing then go to where you change the type of text and color.. and change the color to blue or what ever ever color you want it, it will then print from the color cartridge.*

### Chapter 5 : The buried Mac setting that can save your inkjet's color ink - CNET

*When color ink is expended and black ink still remains, you can continue printing for a short time using only black ink. However, you should replace the expended ink cartridge(s) as soon as possible. See the following section to continue printing temporarily with black ink.*

### Chapter 6 : 3 Ways to Print in Black and White on Epson Printers - wikiHow

*How to Print in Black and White on Epson Printers In this Article: Changing Default Settings on Windows Changing Default Settings on Mac Printing in Black and White Manually Community Q&A This wikiHow teaches you how to print your documents using black-and-white ink on an Epson printer.*

### Chapter 7 : Troubleshooting

*One of the three color ink tanks seems to be always low or out of ink. I often print a document in color when I don't need to because the grayscale option is buried in Preview's print window.*

### Chapter 8 : How Do I Print in Blue Instead of Black? | racedaydvl.com

*Colors the machine can print and colors you see on a monitor are different. Computer monitors can display millions of color as RGB (Red, Green, Blue). The color laser machine uses a 4-color printing process of CMYK (Cyan, Magenta, Yellow, Black).*

### Chapter 9 : Canon Knowledge Base - Print using black ink only (Mac OS X)

*After printing a 4-color message (black, red, yellow, and blue), I saw that it was the black that didn't print. However, the ink level reading was normal. I tried the automatic nozzle and head cleaning but that didn't solve the problem.*